



1. Requirements for ensuring a smooth installation

Windows 10 and Windows 11

1. Your hard drive should have at least 15 GB of free storage space.
2. Is your operating system and CAD platform supported by *hyperMILL*®? Please check this in the [release notes](#) in the **Supported software** section.
3. Log in as a local administrator.
4. Stop the scanning process of your antivirus software.

OPEN MIND also recommends excluding the following directories, file types, processes and services from the virus scan:

Directories			
NC file		Specified by the user	
Post processor		Specified by the user	
CAD file		Specified by the user	
hyperMILL installation		Default path: C:\Programs\OPEN MIND\	
General workspace		hyperMILL® settings -> Application -> Default paths	
Project		hyperMILL® settings -> Document -> Directories	
Licensing software		C:\Program Files (x86)\CodeMeter	
OPEN MIND Roaming		C:\Users\User Name\AppData\Roaming\OPEN MIND	
OPEN MIND temp		C:\Users\User Name\AppData\Local\Temp\OPEN MIND	
<i>hyperMILL</i> ® tmp		C:\Users\Public\ Documents\OPEN MIND\tmp\	
OM ProgramData		C:\ProgramData\OPEN MIND	
File types			
*.3df	*.nc	*.ovz	*.tmpof
*.comp	*.nclist	*.pcf	*.tool



File types			
*.def	*.ncmap	*.pof	*.vis
*.h	*.oma	*.ppcfg	*.vmm
*.hmc	*.omx	*.pprpt	*.vnc
*.hmrep	*.omgcfg	*.settings	.rsf
*.hvz	*.origin	*.so	.his

These file types are trusted as they are generated exclusively by *hyperMILL*®.

Processes		
CodeMeter.exe	GetHS.exe	omCheck_x64.exe
cycrunx64.exe	hmc.exe	omToolDBX64.exe
LicenseManager.exe	omHV64.exe	

Services

Service of CodeMeter.exe

Please have your IT set the antivirus software according to these specifications.